

Live Streaming Notes

- 1) There are 2 mevo camera.
 - a. Ambo
 - b. Altar
- 2) Unplug USB charging cables from each camera and turn on each camera
Put the Ambo cable in the Altar Guild room
To turn on Camera - Turn on from the BACK



Push in button until it Beeps

Camera is ON when there is a GREEN LIGHT on front of camera




RED Light - OFF

GREEN LIGHT- ON

3. PC is on. Just turn on the screen. Bottom right
LOG into LIVE STREAMING PC (PC on the right)
Password → !2727Airline

4. Open VMix Program

Then




Use **OPEN drop Arrow**
Then Choose worship.vmix
(the 1st One)

5. Use Church Ipad


Cameras are slow to appear.

6. If cameras DO NOT appear → open MEVO app


** Configure button on first
camera that shows




**** Click Mevo Hotspot. Wait**



**** Click St. Mark' Office .Wait
** Click DONE**




**** It should say ST. Mark's Office**




For some reason, we have to
Reconnect to Mevo Hotspot
Then back to St. Mark's Office
Wifi!
Click Done . Camera view
Should show in VMix.

Usually all 2 cameras will show. If only 1 camera shows, use the iPad Mevo Camera app and scroll to the second camera and find 2nd camera

On the app → Configure → repeat Instruction #6



7. All 2 camera should show → Ambo, Altar and NDI Presentation-PC




Don't worry about
Black Box

8. Have someone help you to adjust camera views (Doug Wayland always offers)

** ALTAR camera should be ok.


** AMBO - make sure Ambo is centered as best as possible

9. Screen Explained



This is your Active Screen. This is what LIVE Streams This is the Responses

The Left Top Screen is the Screen NEXT to go live. If you Press CUT -- That camera (ambo) goes LIVE



CUT

10) You will need to have the NEXT camera view always READY On the LEFT side. SO when you CUT, you go live with that camera

Generally →

** When FR John is talking, have ALTAR camera live

** When Lay Reader is at the AMBO or Fr John is reading the gospel from the AMBO, have AMBO camera live

** For Songs or long Responses, have NDI Presentaion-PC live

Basically if are switching between Views. Altar, Ambo and NDI Presentaion-PC


The screen on the Upper left is your ACTIVE Live Stream

Always have the next view ready on the Right then press Cut

To get the view in the upper right, click the view from the bottom List!

11) When you are ready to live stream, usually about 5-10 minutes before the service starts, Press the Stream Tab

Wait the Tab will turn RED
Indicating you are live Streaming. I usually Show Altar



When the service is over,

Press Tab again. It will ask you if you really want to end. Click Yes

12) That is it!

Exit the VMix program. You do not need to save.

Turn off the two cameras the same way you turned on.

Check the front of the camera - Red light